


UltraVNC SC 2.0

1. Direct connection

1.1 Viewer


On *somehost* run `vncviewer.exe`



2. Repeater connection

2.1 Viewer


UltraVNC Viewer - 1.3.9.0

 **UltraVNC Viewer**

ID:12345679 ID:1234567

repeater:port repeaterhost:5902

Direct Repeater Cloud

 Show Options

2.2 Server

Helpdesk.txt

[HOST]

Repeater id code 1234567


-autoreconnect ID:1234567 repeaterhost:5500

UltraVnc SC

Internet support
Internet support encryption
Repeater id code 1234567
Repeater enter id code
Using cloud connect

Connect

Dubble Click to make a connection
Before making a connection
Please Call 56 576896 to get your ticket



More Info STOP test

[HOST]

Repeater enter id code

-autoreconnect ID:[ENTERCODE] repeaterhost:5500


UltraVnc SC

Internet support
Internet support encryption
Repeater id code 1234567
Repeater enter id code
Using cloud connect

ENTER YOUR IDE

Connect


Dubble Click to make a connection
Before making a connection
Please Call 56 576896 to get your ticket



More Info STOP test

3. cloud

3.1 Viewer/Server



Helpdesk.txt

[HOST]

Using cloud connect

-cloudserver cloud.uvnc.com

UltraVnc SC


Internet support
Internet support encryption
Repeater id code 1234567
Repeater enter id code
Using cloud connect

Connect

Dubble Click to make a connection


Before making a connection

Please Call 56 576896 to get your ticket



More Info STOP test

Cloud connect ✕


Stop 

Cloud connect server:


Cloud connect code: **1CBD910DA1**

External ip address: 109.133.182.212

If the server is able to connect (orange)



If the same code is found (green)





4. encryption

2.1 Viewer

On *somehost* run `vncviewer.exe`

2.1.1 Activate encryption





Generate 2 keys

sample

20220814_Server_ClientAuth.pubkey

20220814_Viewer_ClientAuth.pkey

Copy 20220814_Server_ClientAuth.pubkey in the winvnc.exe folder

Copy 20220814_Viewer_ClientAuth.pkey in viewer.exe folder

